



EMpower Installation manual

Table of contents

Requirement	2
Mac	3
Troubleshooting	3
Windows / Linux	5
Start the Installation	7
Start EMpower	8

Requirement

For installing and running EMpower:

	Recommended
CPU	64-bit Intel i7 equivalent or better
RAM	16 GB+
Screen Resolution	1920 x 1080
Installation disk space	200MB
Data disk space	50GB + <i>(depends on the survey)</i>
Internet Connection	Required to authenticate license code
SD Card reader	USB 3.0 <i>(or equivalent speed)</i> for data transfer
Monitor Size	13" +

Windows

Versions supported: Windows 10 and up, 64-bit

Permissions required: Must be logged in as Administrator

Linux

Versions tested: Ubuntu 18.04, 64 bit

Permissions required: Standard user

Mac

OS versions tested: 10.11, "El Capitan" and 10.15.4, "Catalina" 64 bit


Note: *User needs to change system setting allowing installation of apps from app store and unidentified developers*

Mac

1. Drag and drop the installer onto the Applications folder to begin the installation.




2. Read the EMpower License Agreement




- If you agree with the terms of the EMpower license agreement, then click the **Agree** button

Troubleshooting

3. Mac OS default security settings block installing EMPower because Phoenix is not a registered developer



4. To continue the installation, go to macOS System Preferences / Security & Privacy and click on **Open Anyway**



Windows / Linux

1. EMpower Setup Wizard by double clicking on the Empower installation executable file. This file will look similar to the example shown below.

Windows: EMpower_v1.###_x86_amd64.exe


Linux: EMpower_v1.###_x_x64.run



- Click Next

3. Installation Folder


- Use the default directory from the installer, or press Browse to select a different directory



- Click Next


3. Hard drive memory space required

- Review the memory space requirement
- Click Next




4. Read the EMpower License Agreement.

- If you agree with the terms select “I accept the license“ option
- Click **Next** button



5. Start the Installation

- Click the **Install** button to begin the installation



The windows installer does not have a back button.

6. Click the **Finish** button to complete the EMPower installation




Start EMpower

1. Click the **EMpower** shortcut icon (Windows / Mac)



- In Linux, run the empower.sh script in the EMpower installation directory
2. The Text “Unlicensed” will appear at the bottom of the **EMpower** application window
 - The **Prepare** module can be used without license



3. The Evaluate and Manage modules can only be used activating the EMpower license, (see EMpower - License activation document)